

PLAN USER GUIDE



Release 26.7
Last Updated: 04 September 2026

Information in this document is subject to change without notice. Companies, names and data used in examples are fictitious.

Copyright ©2026 by InEight. All rights reserved. No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without the express permission of InEight.

Microsoft Windows, Internet Explorer and Microsoft Excel are registered trademarks of Microsoft Corporation.

Although InEight Plan has undergone extensive testing, InEight makes no warranty or representation, either express or implied, with respect to this software or documentation, its quality, performance, merchantability, or fitness for purpose. As a result, this software and documentation are licensed “as is”, and you, the licensee are assuming the entire risk as to its quality and performance. In no event will InEight be liable for direct, indirect, special, incidental or consequential damages arising out of the use or inability to use the software or documentation.

Release 26.7
Last Updated: 04 September 2026

This page intentionally left blank.

CONTENTS

1.1 Plan Quantity Tracking Overview	11
1.1.1 InEight Plan Work Flow	11
1.1.2 Quantity Tracking Terminology	12
1.1.3 Components	14
1.1.4 Component Attributes	17
1.1.5 Claiming Schemes	18
1.1.6 Quantities Sent to InEight Control	20
2.1 Page Navigation	21
Launch Quantity Tracking	24
2.1.1 Standard Grid vs Data Block View	26
2.1.1.1 Standard Grid view	26
2.1.1.2 Data Block view	27
2.1.2 URL Filtering	27
2.2 Columns	28
2.2.1 Move Columns	29
Move Columns	29
2.2.2 Add and Remove Columns	29
Add Additional Columns	29
2.2.3 Sort Columns	31
Sort Columns	31
2.2.4 Filter Columns	32
Filter Columns	32
2.3 Viewsets	34
Create a Viewset	34
2.3.1 Send a viewset	35
Send a viewset	35
2.3.2 Delete a viewset	38
2.4 Data Blocks	39
2.4.1 Component Details Data Block	39
2.4.2 Step Data Blocks	39
2.5 Query Builder	41
2.5.1 Add a Query	41
Add a Query	41
2.6 CBS tree	43

2.7 AWP Filter	44
CHAPTER 3 – CLAIMING SCHEMES	47
3.1 What is a Claiming Scheme?	48
3.1.1 What is the purpose?	48
3.1.2 Claiming scheme setup	49
3.2 Claiming Scheme Management	50
3.2.1 Create a claiming scheme	51
Create a claiming scheme	51
3.2.2 Assign claiming schemes	52
3.2.2.1 Assign to a component	53
3.2.2.2 Assign to a WBS phase code	54
Assign a WBS to a claiming scheme	55
3.2.3 Map claiming schemes by account code	56
3.2.3.3 Manage account code assignments	57
Map claiming schemes by account code	57
3.2.4 Edit a claiming scheme	58
3.3 Import and Export Claiming Schemes	60
3.3.1 Share claiming schemes across projects	60
Import from another project	60
Export to another project	61
3.3.2 Import and export via Excel	62
Export claiming schemes	62
3.3.2.1 Import claiming schemes	63
3.3 Step by Step 1 – Export a claiming scheme template	65
Import claiming schemes	65
3.3.2.2 Correcting import errors	66
4.1 InEight Plan Workflow - Component Management	67
4.2 Component Creation from Scratch	67
4.2.1 Create Components	67
4.2.2 Types of Components	68
4.2.2.1 Assembly Components	69
4.2.2.2 Contract Components	70
4.2.3 Methods of Creating Components	70
4.2.4 Component Attributes	71
4.2.4.3 Validated Fields	71
4.2.4.4 Location	71
4.2.4.5 Engineering	72
4.2.4.6 Using Component Attributes	73

4.2.4.7 Split Contract Components	73
4.2.4.8 Validated lists in Field attributes	74
4.2.4.9 Schedule Components	75
4.2.4.10 Project Values	76
4.2.5 Component Creation	77
Create a Component from Scratch	77
Copy an Existing Component	80
Split an Existing Component	81
Bulk Edit Components	82
4.2 Step by Step 1 – Bulk Delete Components	82
4.3 Component Creation from Import	82
4.3.1 Import Template	83
Create Components from Excel Import	84
4.4 Component Audit Log	90
4.4.1 Summary	90
4.4.2 Component Export History	91
4.4.3 Considerations	92
4.5 Default Components	92
4.5.1 What are Default Components?	92
4.5.2 Enable and Refresh Default Components	93
4.5.2.1 Considerations for Enabling Default Components	93
4.5 Step by Step 1 – Enable and Refresh Default Components	94
4.5.2.2 Delete default components	94
5.1 InEight Plan Workflow - Quantity Claiming	97
5.2 Quantity Claiming	97
5.2.1 Process for claiming quantities	97
5.2.2 Why claim at a component level?	98
5.2.3 Claiming in the Standard Grid View	98
Quantity Claiming (Standard Grid View)	99
5.2.4 Over claim component quantity	101
5.2.5 Claiming in the Data Blocks View	103
Quantity Claiming (Data Blocks View)	103
5.2 Step by Step 1 – Apply Installed Quantity to All	104
5.3 Edit Claimed Quantities	104
5.3.1 Quantity Joined	105
5.3.2 Quantity Editing	105
Edit Claimed Quantity	106
Batch Edit Claimed Quantity	109

STEP-BY-STEP PROCEDURES

Launch Quantity Tracking	24
Move Columns	29
Add Additional Columns	29
Sort Columns	31
Filter Columns	32
Create a Viewset	34
Send a viewset	35
Add a Query	41
Create a claiming scheme	51
Assign a WBS to a claiming scheme	55
Map claiming schemes by account code	57
Import from another project	60
Export to another project	61
Export claiming schemes	62
3.3 Step by Step 1 – Export a claiming scheme template	65
Import claiming schemes	65
Create a Component from Scratch	77
Copy an Existing Component	80
Split an Existing Component	81
Bulk Edit Components	82
4.2 Step by Step 1 – Bulk Delete Components	82
Create Components from Excel Import	84
4.5 Step by Step 1 – Enable and Refresh Default Components	94
Quantity Claiming (Standard Grid View)	99
Quantity Claiming (Data Blocks View)	103
5.2 Step by Step 1 – Apply Installed Quantity to All	104
Edit Claimed Quantity	106
Batch Edit Claimed Quantity	109

EXERCISES

This page intentionally left blank.

1.1 PLAN QUANTITY TRACKING OVERVIEW


As one of the applications within the InEight portfolio of products, InEight Plan is a tool for engineers and superintendents to plan work and track quantities during the execution of their project.

Plan is organized into two modules:

Plan Modules	
Work Packaging	Creating and managing work packages.
Quantity Tracking	Creating and managing components and claiming schemes. Claiming completed quantities.

1.1.1 InEight Plan Work Flow

This course focuses on the Quantity Tracking module of InEight Plan.




1.1.2 Quantity Tracking Terminology

Plan Quantity Tracking uses some key terminology to describe how the work is broken down for tracking.

The table below defines each of the key terms you should know.


Term	Definition	Managed In..
CBS (Cost Breakdown Structure)	Hierarchy of budgeted work activities (cost items) in a project.	 Control
WBS (Work Breakdown Structure)	Code assigned to terminal cost items for tracking purposes.	 Control
ACS (Account Code Structure)	Standard Classification code used for benchmarking similar types of work between projects.	 Control
Component	Item or element of work used for maintaining quantities.	 Plan
Claiming Scheme	A method used for tracking component progress via use of sublevel tasks (steps).	 Plan

The relationship between these terms is shown in the following diagram:



Scenario

You are a structural steel field engineer responsible for accurately tracking installation progress for a steel structure project. See image below. The structural steel cost item is measured in tons, but steel is installed by piecemark, and it needs to be tracked as such. There are multiple steps to structural steel installation that are all coded to the same cost code, and you need a way to track completion of the different steps as well. You also want to easily communicate to your foreman what he needs to accomplish each day to stay on schedule and on budget.




The image above depicts a layout for a steel structure project. The project consists of erecting 30 separate steel structures on opposite sides of a road. Each structure or module has been assigned a number 1-30.

1.1.3 Components

Within the InEight Control application, cost items are identified by a WBS Phase Code (commonly referred to as simply the WBS). A unique WBS is assigned to each cost item in the CBS, including superior and terminal items. The WBS codes can be set up to be automatically assigned or manually input.

Tasks			Task Det.. < >		
	CBS Position	Description	WBS Phase Code	Forecast TO Qty	UOM
☐	1	Job Overhead	1002	1.00	Lump Su..
☐	2	Earthwork	1069	10,000.00	CY
☐	3	Concrete	1071	10,000.00	CY
☐	▼4	Structural Steel	1073	1,000.00	Ton
☐	4.1	Erect Steel - Heavy	1074	800.00	Ton
☐	4.2	Erect Steel - Light	1005	200.00	Ton
☐	4.3	Bolted Connections	1006	2,000.00	Ea
☐	▼5	Materials	1084	1.00	Each

In InEight Plan, the Quantity Tracking module allows you to break down quantities into more manageable tasks to track and claim against. You accomplish this by breaking down your WBS Phase Code quantity into smaller pieces called components.



Referring to the scenario above, your project has an 'Erect Steel – Light' cost item with a WBS Phase Code of 1005, as seen in the CBS register of the Control application.

Steel Structure Job (105091)

Control

Workspaces

CBS

ACS

Actions

Tasks

CBS position

Description

1

Job Overhead

^ 2

Earthwork

2.1

Earthwork Review

2.2

Earthwork

3

Concrete

^ 4

Structural Steel

4.1

Erect Steel - Heavy

4.2

Erect Steel - Light

4.3

Bolted Connections

4.4

Module XXX - Erect...

Task details

WBS phase code

Forecast (T/O) quantity

UoM

1002

1.00

Lump Sum

1069

10,000.00

CY

1003

1.00

Each

1004

10,000.00

CY

1071

10,000.00

CY

1073

1,000.00

Ton

1074

350.00

Ton

1005

200.00

Ton

1006

2,000.00


Ea

1087

800.00

Ton

For tracking purposes, in the Quantity Tracking module of Plan, you can break down the 'Erect Steel – Light' WBS Phase Code into distinct components by structural steel piecemark:



Each component has a measured quantity:


Component	Quantity
A14: Beam	0.44 Tons
F16: Beam	0.45 Tons
C23: Cross Brace	0.26 Tons

The sum of the quantities for each component adds up to the total quantity for the assigned WBS.

1.1.4 Component Attributes

Components can have a myriad of attributes assigned to them to help organize and store pertinent information that can be used for filtering and reporting. These include but are not limited to:


- Schedule ID
- Discipline
- Area
- System
- Customizable Attributes



In Lesson 4 – Component Management, you will learn how to create components either through import from an Excel template or by creating them manually.

1.1.5 Claiming Schemes

Claiming schemes break components down further, to a sequence of steps, so that foremen can track the individual steps as the installation of the component progresses. Each step has a weighted rule of credit, based on percentages, that will progress the overall component.




Claiming schemes can be assigned at either the component, WBS, or Account Code level. If a claiming scheme is assigned at the WBS level, then every component that is assigned to that WBS will automatically inherit the same claiming scheme.

The level at which claiming schemes will be assigned (Account Code, WBS, or component) will typically be dictated during project initiation in the project settings. See Lesson 3 – Claiming Schemes for more details on assigning claiming schemes.

For example, you may break down the 'A14: Beam' component into the following steps for tracking in the field:


Claiming Scheme for 'A14: Beam' Component		
Step	Description	Percentage
Step 1	Shakeout/Transport	15%
Step 2	Erect/Bolt Up	45%
Step 3	Final Torque	30%
Step 4	QC Verification	10%

The diagram below shows how the claiming scheme relates to the component, WBS Phase Code, and Account Code.



In the field, the foreman can indicate when each step has been completed for a specific component. By indicating Step 1: Shakeout/ Transport is complete for 'A14: Beam', this will claim the component is 15% completed. After syncing this information to InEight Control, 15% of the quantity for A14: Beam will be added to the total quantity complete for that WBS code which will drive the earned value.

The diagram below shows the flow of quantity claiming through components and claiming schemes.



1.1.6 Quantities Sent to InEight Control


The quantities tracked at the component level will “roll up” to the assigned WBS Phase Code and be available for progress analysis and forecasting in the Control application. [Learn more about syncing in the Control Knowledge Library.](#)

In this example, the quantities claimed for steel components roll up to the ‘Erect Steel – Light’ WBS item, which then gets sent to Control upon request.


2.1 PAGE NAVIGATION

To launch the Plan application, you must first open the InEight software in your web browser, using the link provided by your manager or facilitator.

Open the **All projects & organizations** page from the Main menu.




On the Projects tab you can select any project you are associated with. If your project is not shown on the initial screen, you can search by selecting the **Search** icon in the top right corner.



The screenshot shows a web application interface with a table titled "All projects & organizations". The table has columns for Name, Stat., Organization, Created by, Created on, Original contract, Contract number, Date project start, Contract date, Original contract, and Original duration. A search icon is highlighted in the top right corner of the table area.

Name	Stat.	Organization	Created by	Created on	Original contract	Contract number	Date project start	Contract date	Original contract	Original duration
				07/06/2021 12:29:34			09/09/2019	09/09/2019	09/09/2019	1
				07/06/2021 9:03:18 AM						
				07/06/2021 10:13:31						
				07/09/2021 10:50:48						
				07/12/2021 3:15:06 AM		2021 06 09	08/30/2021	06/09/2021		
				08/04/2021 11:22:04						
				06/01/2020 2:05:49 PM			06/09/2021		05/09/2023	700
				07/09/2021 12:00:54			07/07/2021			
				07/28/2021 10:13:22						
				07/19/2021 5:22:47 PM						
				07/28/2021 12:18:33						
				07/29/2021 10:43:07						
				07/07/2021 6:49:42 AM						
				08/03/2021 3:37:21 PM						
				07/08/2021 11:17:19						
				07/02/2021 4:45:19 AM						
				07/21/2021 7:09:31 AM						
				06/21/2021 8:04:56 AM						
				06/07/2021 8:51:43 AM			06/02/2021			
				06/17/2021 5:25:49 AM						
				12/04/2020 5:59:29 PM			06/01/2021			
				12/04/2020 5:59:29 PM						
				12/04/2020 5:59:29 PM						
				12/04/2020 5:59:29 PM			08/04/2021			
				12/04/2020 5:59:29 PM						


When you select a project, it takes you to the Project home page.




The screenshot shows the "Project home" dashboard. It features a left sidebar with navigation links: Model, Document, Schedule, Design, Dashboard, Quantity forecasting, Engineering, Estimate, Control, Workspaces, Project library, Plan, Quantity tracking, Work packaging, Progress, Daily planning, Time center, Weekly time sheet, and Capital. The main content area is divided into several sections: Links (Organization, LaunchPad, Project), Project notes, Settings (Project and application settings), Project contract summary (Actual values, Original project value), Control (Manage budgets and forecasts), Work packaging (Group work into plans and packages), Contracts (Status, Count), Change milestones (Project dates, Contract, Forecast), Quantity tracking (Build components and document quantities), Daily planning (Assign tasks for your crew), Supporting documents, Bid packages (Awarded, Unawarded), and Change status (Closed, In Process, Active).

From here, you can launch Plan Quantity tracking in several ways:


- Clicking the Quantity tracking Launch application tile




- Selecting Plan > **Quantity tracking** from the left menu



- Selecting Plan > **Quantity tracking** from the second-level drop-down menu for a specific organization or project at the top of the page



- Selecting Plan > **Quantity tracking** from the app launcher icon in the upper-right corner of the page



The following steps walk you through launching Quantity tracking using the second-level drop-down menu at the project level.

Launch Quantity Tracking

1. From the Projects tab of the **All projects & organizations** page, click on the project name hyperlink to select a project.
This opens the Project home page.
2. From the Project home page, click the **main menu** icon, and then click the **project name** to open the second-level menu.
3. From the second-level drop-down menu, open the **Plan** drop-down menu, and then select **Quantity tracking**.

This brings you to the Quantity tracking page.

Overview - Quantity Tracking Home Page (Standard Grid)

Title		Description
1	Actions	Contains available actions for the current tab.
2	Left toolbar	Options to add, edit, bulk edit, delete, copy, and split components.

Overview - Quantity Tracking Home Page (Standard Grid) (continued)

Title		Description
3	Grid view options	• Row density: Lets you change the spacing between rows. • View as data blocks: Changes to data block view.
4	Views	Lets you create, save, change and share views.
5	Import, Export, and Save claiming	• Options to import and export data to Microsoft Excel. • Lets you save claimed quantities.
6	Query options	• Filter: Opens the Query builder side panel to filter components. • (Clear) Filter: Clears all column filters. • CBS tree: Opens the CBS tree to filter by CBS. See CBS tree for more information. • AWP filter: Filter associated work packages to quickly find components associated with the selected work packages • Clear CBS and user queries: Clears all filters from the Query builder and the CBS tree.
7	Components	Shows components in a table according to the applied query and filters.
8	Results and selection counts	Shows the counts of results and selected components. Choose whether to view selected components or clear your selection

Name	Parent record	Assembly	Type	Discipline / Commodity	Claiming scheme	WBS	Description	Quantity	To date quantity	UoM	% Complete	WBS forecast QTY	WBS planned QTY	WBS to
Module 30 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 30 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 30 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 30 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 29 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 29 - A7 Co.	1.00000	0.90000	Ea	90	2,000.00000	60.00000	0.90000
Module 29 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 29 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 28 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 28 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 28 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 28 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 27 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 27 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 27 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 27 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 26 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 26 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 26 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 26 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 25 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 25 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 25 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 25 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 24 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 24 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 24 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 24 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 23 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 23 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 23 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 23 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 22 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 22 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 22 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 22 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 21 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 21 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 21 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 21 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 20 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 20 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 20 - A6 Co.			Activity	Metals	Bolted Connection...	1006	Module 20 - A6 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000
Module 19 - A7 Co.			Activity	Metals	Bolted Connection...	1006	Module 19 - A7 Co.	1.00000	0.00000	Ea	0	2,000.00000	60.00000	0.90000

2.1.1 Standard Grid vs Data Block View

The Components page has two separate views: Standard Grid view and Data Block view. By default, the Components page opens in the Data Block view.

2.1.1.1 Standard Grid view

The Standard Grid view offers a traditional spreadsheet look with rows and columns.


Name	Parent record	Assembly	Type	Discipline / Commodity	Claiming scheme	WBS	Description	Quantity	To date quantity	UoM	% Complete	WBS forecast	WBS planned	WBS to date	% WBS QTY	Work pac
1083 - Pond - DIA.			Activity	Grading	511001 - Mas.	1083	Pond - DIA3P...	6,157.00000	3,206.00000	CV	52.07081	35,834.00000	35,834.00000	11,835.00000	33.02729	
1083 - Pond - DIA.			Activity	Grading	511001 - Mas.	1083	Pond - DIA3P...	8,046.00000	3,057.00000	CV	37.99403	35,834.00000	35,834.00000	11,835.00000	33.02729	
1083 - Pond - DIA.			Activity	Grading	511001 - Mas.	1083	Pond - DIA4P...	7,564.00000	5,572.00000	CV	73.66473	35,834.00000	35,834.00000	11,835.00000	33.02729	
1083 - Pond - DIA.			Activity	Grading	511001 - Mas.	1083	Pond - DIA5P...	6,228.00000	0.00000	CV	0	35,834.00000	35,834.00000	11,835.00000	33.02729	
1083 - Pond - DIA.			Activity	Grading	511001 - Mas.	1083	Pond - DIA7P...	1,439.00000	0.00000	CV	0	35,834.00000	35,834.00000	11,835.00000	33.02729	
1083 - Pond - DIA.			Activity	Grading	511001 - Mas.	1083	Pond - DIA7P...	1,919.00000	0.00000	CV	0	35,834.00000	35,834.00000	11,835.00000	33.02729	
1083 - Pond - DIA.			Activity	Grading	511001 - Mas.	1083	Pond - DIA7P...	4,481.00000	0.00000	CV	0	35,834.00000	35,834.00000	11,835.00000	33.02729	
1087 - Pond - DIA.			Activity	Grading	511002 - Mas.	1087	Pond - DIA3P...	6,157.00000	0.00000	CV	0	35,834.00000	35,834.00000	13,258.58000	37.00000	
1087 - Pond - DIA.			Activity	Grading	511002 - Mas.	1087	Pond - DIA3P...	8,046.00000	8,046.00000	CV	100	35,834.00000	35,834.00000	13,258.58000	37.00000	
1087 - Pond - DIA.			Activity	Grading	511002 - Mas.	1087	Pond - DIA4P...	7,564.00000	1,395.00000	CV	18.44262	35,834.00000	35,834.00000	13,258.58000	37.00000	
1087 - Pond - DIA.			Activity	Grading	511002 - Mas.	1087	Pond - DIA5P...	6,228.00000	0.00000	CV	0	35,834.00000	35,834.00000	13,258.58000	37.00000	
1087 - Pond - DIA.			Activity	Grading	511002 - Mas.	1087	Pond - DIA7P...	1,439.00000	0.00000	CV	0	35,834.00000	35,834.00000	13,258.58000	37.00000	
1087 - Pond - DIA.			Activity	Grading	511002 - Mas.	1087	Pond - DIA7P...	1,919.00000	0.00000	CV	0	35,834.00000	35,834.00000	13,258.58000	37.00000	
1087 - Pond - DIA.			Activity	Grading	511002 - Mas.	1087	Pond - DIA7P...	4,481.00000	3,817.58000	CV	85.19482	35,834.00000	35,834.00000	13,258.58000	37.00000	
1091 - Pond - DIA.			Activity	Grading	511003 - Mas.	1091	Pond - DIA3P...	3,694.00000	2,304.00000	CV	59.66432	21,501.00000	21,501.00000	8,011.00000	37.25873	
1091 - Pond - DIA.			Activity	Grading	511003 - Mas.	1091	Pond - DIA3P...	4,828.00000	1,677.00000	CV	34.73488	21,501.00000	21,501.00000	8,011.00000	37.25873	
1091 - Pond - DIA.			Activity	Grading	511003 - Mas.	1091	Pond - DIA4P...	4,538.00000	4,130.00000	CV	91.00926	21,501.00000	21,501.00000	8,011.00000	37.25873	
1091 - Pond - DIA.			Activity	Grading	511003 - Mas.	1091	Pond - DIA5P...	3,737.00000	0.00000	CV	0	21,501.00000	21,501.00000	8,011.00000	37.25873	
1091 - Pond - DIA.			Activity	Grading	511003 - Mas.	1091	Pond - DIA7P...	864.00000	0.00000	CV	0	21,501.00000	21,501.00000	8,011.00000	37.25873	
1091 - Pond - DIA.			Activity	Grading	511003 - Mas.	1091	Pond - DIA7P...	1,151.00000	0.00000	CV	0	21,501.00000	21,501.00000	8,011.00000	37.25873	
1091 - Pond - DIA.			Activity	Grading	511003 - Mas.	1091	Pond - DIA7P...	2,689.00000	0.00000	CV	0	21,501.00000	21,501.00000	8,011.00000	37.25873	
1095 - Pond - DIA.			Activity	Grading	511004 - Loc.	1095	Pond - DIA3P...	2,463.00000	0.00000	CV	0	14,334.00000	14,334.00000	3,218.00000	22.45012	
1095 - Pond - DIA.			Activity	Grading	511004 - Loc.	1095	Pond - DIA3P...	3,218.00000	3,218.00000	CV	100	14,334.00000	14,334.00000	3,218.00000	22.45012	
1095 - Pond - DIA.			Activity	Grading	511004 - Loc.	1095	Pond - DIA4P...	3,026.00000	0.00000	CV	0	14,334.00000	14,334.00000	3,218.00000	22.45012	
1095 - Pond - DIA.			Activity	Grading	511004 - Loc.	1095	Pond - DIA5P...	2,491.00000	0.00000	CV	0	14,334.00000	14,334.00000	3,218.00000	22.45012	

2.1.1.2 Data Block view

The Data Block view groups columns for a cleaner viewing experience focused on claiming. Data Blocks are covered in more detail in the Data Blocks topic.

The screenshot displays the 'Data Block view' interface. It is divided into two main panels. The left panel, titled 'Component details', shows a list of components with columns for Name, Work package ID, Assembly, and Discipline / Commodity. The right panel, titled 'Step 1', shows a table with columns for Step name, Step %, Complete, Quantity, Installed qty, This period qty, and UoM. The 'Complete' column has checkboxes, and the 'Quantity' and 'Installed qty' columns have numerical values. A 'View as' button is visible in the top right corner of the interface.

Easily switch between the two views by clicking the **View as** button on the toolbar.




2.1.2 URL Filtering

Custom URLs can be generated from a source program, which can be shared as a direct link to Quantity tracking that filters to a specific WBS code.

The exact URL depends on your organization setup but the URL ends with *AppPlan/QuantityPlan/QuantityPlanLaunch?projectId=[ProjectID]&WBSPhaseCode=[WBS]*.

When the URL is accessed, the grid shows with the applied filters and the URL returns to its default value for the Plan Quantity tracking page. The component edit slide-out shows the matching records.



The system will filter the following columns which can be combined when creating a custom URL string:

- projectId (required)
- componentname
- scheduleofvaluesitemid
- wbsphasecode
- area
- segment
- system
- subsystem
- turnover
- percentagecomplete

2.2 COLUMNS


Customize columns according to your preferences. Changes you make to the placement of your columns will be retained the next time you access any page you have customized.

2.2.1 Move Columns

Drag and drop to move a column from one place to another to customize your view.


Move Columns

- 1. In the Standard Grid view of the Quantity Tracking module, click on and hold a column header.



	Name	Parent record	Assembly	Type	Discipline / Commod...	Claiming sc...	WBS	Description
☐	Cross Brace Assem...		Cross Brace Assem...	Assembly				
☐	Module 30 - A7 Co...			Activity	Metals	Bolted Conne...	1006	Module 30 - A...
☐	Module 30 - A6 Co...			Activity	Metals	Bolted Conne...	1006	Module 30 - A...
☐	Module 29 - A7 Co...			Activity	Metals	Bolted Conne...	1006	Module 29 - A...
☐	Module 29 - A6 Co...			Activity	Metals	Bolted Conne...	1006	Module 29 - A...

- 2. Drag and drop the column in a new location.




	Name	Parent record	Assembly	Type	Discipline / Commod...	Claiming sc...	WBS	Description
☐	Cross Brace Assem...		Cross Brace Assem...	Assembly				
☐	Module 30 - A7 Co...			Activity	Metals	Bolted Conne...	1006	Module 30 - A...
☐	Module 30 - A6 Co...			Activity	Metals	Bolted Conne...	1006	Module 30 - A...
☐	Module 29 - A7 Co...			Activity	Metals	Bolted Conne...	1006	Module 29 - A...

2.2.2 Add and Remove Columns


Add or remove columns to customize your view and work more efficiently when in the Standard Grid view.

Add Additional Columns


- 1. From the Standard Grid view, select the **Column Chooser** icon to open a pop-up window where you can search for and select columns.



- In the selected columns list on the right, highlight all columns. To do this, select the first item in the list, press and hold the Shift key, scroll down the list, and select the last item in the list. Then, select the **left pointing arrow**.




- In the Available columns list on the left, type a column name in the search bar or use the scroll bar to find a column by name. Select a column from the **Available columns list**.



A yellow caution icon shows when a column is unavailable.

- Select the **right facing arrow**.
- Repeat steps three and four as needed for your project.



6. Click **Save**.

2.2.3 Sort Columns

Sort in ascending or descending (both for alpha and numeric fields) order on any column by clicking one time on the column header.

Sort Columns

1. In the Standard Grid view of the Components page, click on any column header to sort the column in ascending order.

Discipline / Commodity	Claiming sch...	Quantity	Description	To date quan...
Metals	Erect Steel - L...	0.10000	Module 1 - E2...	0.00000

- Notice the yellow up arrow designating you are sorting in ascending order
2. Click on a column header again (a second time) and the column will filter in descending order.

Discipline / Commodity	Claiming sch...	Quantity	Description	To date quan...
Metals	Bolted Conne...	1.00000	Module 1 - A6...	0.00000


- Notice the yellow arrow is now pointing down
3. Click the same column header a third time to remove the applied sorting feature.

2.2.4 Filter Columns


Filter columns as a way to see relevant information pertaining to your specific needs.

Filter Columns

1. In standard or data block view, type your filtering criteria in the text box of any column header. A drop-down list shows matching criteria.




2. Select a value from the drop-down list or press **Enter**.
3. Optionally, click the **Filter** icon to select a different operator.



4. Click the **Clear** icon to remove the filter.

You can apply filters to multiple columns at the same time.

To clear all column filters at the same time, click the **Clear applied filters** icon on the left of the Quantity tracking page.




If you hover over the icon, a word bubble shows the current applied column filters.

2.3 VIEWSETS


You can create a saved view of your page so that you can always revert to it. This saved view is called a viewset.

Create a Viewset


- 1. Select the **View** drop-down arrow to save your current view.



- 2. Select **Save current viewset as** from the viewset drop-down list.




- 3. In the dialog box, type a name.



4. Click **Save**.

When making changes to the quantity tracking layout, you will see an **unsaved view** option in the view menu. This lets you know changes have not been saved.



Each viewset is user-specific. However, viewsets do not carry over from the Standard Grid view to the Data Block view. You have to create your viewsets for both the Standard Grid and Data Block views.

2.3.1 Send a viewset

Certain permissions are needed to send viewsets to roles.

You can send views to all users that have a certain role. You can also send it to specific projects or full organizations. To send to a project, you must be a user on that project or in that organization.

Send a viewset

1. Open the viewset you want to share.
2. Open the View drop-down list, and then select **Send current view**.

3. Select **Users** or **Projects** from the drop-down list, and then search by user name or project. You can add multiple users and projects.

When you share a view with another project, any project-specific fields are not shown in the receiving project. You can select the Share view as global template option.

Send view (Demo 2312) to

Users

Search for a user

Send to

Users

No users selected

Projects

No projects selected

⊖

Remove all

☒ Share view as global template.

Cancel

Click **Send**. A notification is sent to the selected users and the viewset is available in their drop-down list, along with the sender's name and the date when the viewset was sent.

2.3.2 Delete a viewset

Delete a viewset by selecting the delete icon in the drop-down list directly in the viewset.

2.4 DATA BLOCKS

Each data block is a set of columns grouped together based on categories of information that let you focus on claiming. Data blocks help you to organize and manage all the columns on a page.

The information in each data block is displayed in a grid-like format, maintaining a spreadsheet look and feel.

Component details				Step 1						
Name	Work package	Assembly	Discipline / Commodity	Step name	Step %	Complete	Quantity	Installed qty	This period qty	Unit
01-10-007 - MCK E...	40100		Electrical	Install	100	☐	1,794.000000	0.000000	0.000000	Ex
01-04-016 - Modul...	40100		Electrical	Install Prep	5	☐	11,312.000000	0.000000	0.000000	Ex
01-02-007 - Modul...	40100		Electrical	Install Prep	5	☐	11,312.000000	0.000000	0.000000	Ex
01-02-020 - 300W ...	40100		Electrical	Install Prep	5	☐	12,056.000000	10,410.000000	0.000000	Ex
01-03-026 - 300W ...	40100		Electrical	Install Prep	5	☐	12,056.000000	0.000000	0.000000	Ex
01-02-017 - 300W ...	40100		Electrical	Logistics Offload	100	☒	12,992.000000	12,992.000000	0.000000	Ex
01-04-023 - 420W ...	40100		Electrical	Logistics Offload	100	☒	11,208.000000	11,208.000000	0.000000	Ex
03-0300.03.0.0 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.1.1 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.1.2 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.0 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.1 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.2 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.3 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.4 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.5 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.6 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.7 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.8 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.9 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.10 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.11 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.12 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.13 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.14 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.15 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.16 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.17 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.18 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.19 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex
03-0300.03.2.20 - MCK...	40100		Electrical	Install	100	☐	8.000000	0.000000	0.000000	Ex

2.4.1 Component Details Data Block

The Component details data block on the left side of the page shows basic information about components so you can easily identify, sort, and filter them while claiming.

Component details shows a maximum of seven columns, which limits how much you have to scroll left and right. The Name column is required. You can choose the other six columns.

To choose which columns are shown, click **Manage detail columns**.

2.4.2 Step Data Blocks

The Step data blocks on the right side of the page show claiming information for each step. You can enter quantities and mark steps complete directly in the data blocks.

You can choose which steps and columns are shown in the Step data blocks. If you want to claim only for a certain step for all components, you can choose only that step to be visible.

To choose what steps and columns are shown, click **Manage step columns**.

You can use the Apply installed quantity to all button at the top of a step data block to apply an installed quantity to all components in your current view.

You can only apply installed quantity up to 50 components at a time, so you must filter your view first to show only the components you want to apply the installed quantity to.

When you click **Apply installed quantity to all**, you can choose to apply an amount or a percentage. After you enter a value, click **Apply**.

If you apply a certain amount that exceeds a component's remaining quantity, all the remaining quantity is installed.

The screenshot shows a software interface with a table and a modal dialog. The table has two columns: 'Quantity' and 'Installed qty'. The 'Quantity' column has a dropdown menu and a filter icon. The 'Installed qty' column has a dropdown menu and a filter icon. The table contains five rows of data, all with '20,380.00000' in the 'Quantity' column and '0.00000' in the 'Installed qty' column. Above the table, there are buttons for 'Manage step columns' and 'Save claiming'. A red button labeled 'Apply installed quantity to all' is highlighted. A modal dialog is open, showing two options: 'Installed quantity(or maximum remaining)' and 'Installed quantity %'. The 'Installed quantity %' option is selected. A text input field next to it contains the value '75'. At the bottom of the dialog are 'Cancel' and 'Apply' buttons.

Quantity	Installed qty
20,380.00000	0.00000
20,380.00000	0.00000
20,380.00000	0.00000
20,380.00000	0.00000
20,380.00000	0.00000

Dialog options:

- ☐ Installed quantity(or maximum remaining)
- ☒ Installed quantity %

Input field: 75


Buttons: Cancel, Apply

After you apply the installed quantity, the changes are flagged as pending in each row until you click **Save claiming**.

2.5 QUERY BUILDER

The Query builder lets you build queries with multiple conditions to filter the entire table of components. You can add, edit, delete, and share queries with others.

To open the Queries slide-out panel, click the **Query** icon on the left side of the page.



2.5.1 Add a Query

A query is made up of conditions that are made up of columns, values, and operators that connect the columns and operators. Multiple conditions can be grouped as And or Or statements.

The following step by step shows you how to add a query, apply it, and then save it for future use.

Add a Query


1. Click the **Query** icon on the left side of the page to open the Queries slide-out panel.
2. Click the **Add** icon. The Query builder opens.
3. Select a column and operator from the drop-down lists.
4. Enter a value that you want to filter the column for.

5. Optionally, click the **Add** icon to add more conditions, and then click **And** or **Or** to change how the conditions are grouped.
6. Click **Apply** to update results immediately.
7. Click **Save query**.

2.6 CBS TREE

The CBS tree is a filter in Quantity tracking that shows the InEight Control WBS Structure, which helps you filter components to the CBS you want without jumping between Plan and Control.

To open the CBS tree in Quantity tracking, click the **CBS tree** icon on the left side of the page. The CBS tree slide-out panel opens.




You can expand and collapse levels of the CBS tree using the arrow icons or the Expand all and Collapse all buttons. To select CBS items to filter for, click one or more CBS items, and then click **Apply**. The components list refreshes to show only components that match the selected CBS items.

To clear the CBS query, click either **Reset** in the CBS tree slide-out panel or click the **Clear CBS and user queries** icon to the left of the panel.


2.7 AWP FILTER

The AWP filter lets you filter associated work packages which helps you can quickly find the components associated with the selected work packages.

To filter components by work package, click the **AWP filter** icon on the left side of the Quantity tracking page. The AWP filter slide-out panel opens.



Select one or more work packages, and then click **Apply** to filter the list of components.



All the components associated to the selected work packages show.

Actions

Manage detail columns

Component details					
	Name	Work package ID	Assembly	Discipline / Commodity	Claiming schedule
☐	Sams...	42169		Operational Support	301002 - Site S
☐	Sams...	42169		Operational Support	301002 - Site S
☐	Sams...	42169		Operational Support	301002 - Site S
☐	Sams...	42169		Operational Support	301002 - Site S
☐	Sams...	42169		Civil Utilities	521011 - Utility
☐	Sams...	42169		Civil Utilities	521011 - Utility
☐	Sams...	42169		Civil Utilities	521011 - Utility
☐	Sams...	42170		Aggregates and Paving	530004 - Insta
☐	Sams...	42170		Aggregates and Paving	530004 - Insta
☐	Sams...	42170		Aggregates and Paving	530004 - Insta
☐	Sams...	42170		Aggregates and Paving	530004 - Insta

View: Current viewset

Manage step columns

Save claiming

Apply installed quantity to all

Step name	Complete	Installed qty	This period qty	UoM
Install	☒	3,000.00000	0.00000	SY
Install	☒	3,000.00000	0.00000	SY
Install	☒	3,000.00000	0.00000	SY
Install	☒	3,000.00000	0.00000	SY
Excavate Trench	☒	60.00000	0.00000	LF
Excavate Trench	☒	60.00000	0.00000	LF
Excavate Trench	☒	80.00000	0.00000	LF
Step 1	☒	51,325.80000	0.00000	Ton
Step 1	☒	42,170.14000	0.00000	Ton
Step 1	☒	51,150.80000	0.00000	Ton
Step 1	☒	26,207.00000	0.00000	Ton

Select **Reset** or **Clear CBS and user queries** to clear or reset the applied filter.

Steel Structure Training Job | 105091 / Plan / Quantity tracking

Actions

AWP filter

Search...

North

CWP- North Area Steel Erection-12

South

Unassociated packages

IWP-test-9

IWP-mn,n-5

CWP-hkh-4

Clear CBS and user queries

Reset

Apply

Component details

	Name	Work package ID
☐	1069	5
☐	1085	5

Displayed results: 2 | Selected: 0 | View selecte

This page intentionally left blank.

CHAPTER 3 – CLAIMING SCHEMES

3.1 WHAT IS A CLAIMING SCHEME?

A claiming scheme is a formula used to record partial progress of installed quantities. The installation sequence is broken down by steps or milestones with each being assigned a completion percentage based on the level of effort required. This scheme allows progressive tracking of work as it advances, rather than waiting until all work is complete.

Claiming schemes are especially useful when work is completed over multiple activities or phases. For example, an installation might involve material handling, assembly, finalization, and quality verification. By defining these steps in advance and assigning appropriate weightings, progress can be reported incrementally as each step is completed.

Claiming schemes:

- Allow you to track your claiming in one central location
- Reduce your need for individual side spreadsheets
- Improve transparency for which portions of work have been completed
- Keep claiming consistent with a clear breakout of quantities reserved for specific activities
- Communicate actual work steps to field teams when completing their plan

3.1.1 What is the purpose?

Quantity tracking and claiming are foundational to accurate cost and performance reporting.

Completed quantities drive:

- Earned budget
- Overall percent complete
- Forecasted cost at completion


Delaying progress reporting until all steps are finished can hide issues and delay visibility of potential schedule or cost impacts. For this reason, claiming is typically performed at short intervals, such as daily or weekly, to provide up-to-date insight into project performance.

Accurate progress measurement at short intervals allows teams to identify negative trends early and respond in a timely manner. Claiming schemes support this by structuring work into measurable portions that can be reported incrementally. By assigning each step a percentage based on relative effort, progress reporting more accurately reflects work performed, rather than defaulting to an all-or-nothing approach.

3.1.2 Claiming scheme setup

Claiming schemes are applied to activities or commodities based on project configuration. They are typically organized by discipline or commodity type, allowing teams to standardize how progress is measured across similar work.

In Plan, each discipline or commodity type includes a default claiming scheme consisting of a single step representing 100% completion.



While this provides a starting point, most workflows require more detailed schemes that break work down into multiple steps for incremental progress tracking.

It is also common to define multiple claiming schemes within the same discipline or commodity type. Different types of work often require different step structures to accurately reflect how progress is performed and measured.

A well-designed claiming scheme breaks work down into a small number of meaningful steps that reflect how the work is actually performed in the field. Each step should represent a distinct phase of progress and be assigned a percentage based on the relative effort required.

Components > Disciplines and claiming schemes

Claiming Scheme Details

Assign WBS

Assign Account Code

Disciplines

Commodities

Claiming scheme Name

☐ Grading

☐ Instrumentation

☐ Job Related Overhead

☐ Mechanical Equipment

☐ Metals

☒ Erect Steel - Light

☐ Mining

☐ Misc Specialty Work

☐ Offshore Fabrication

☒ Bolted Connections

☒ Erect Steel - Light

Name

Erect Steel - Light

Step name	Rule type	% claiming	Schedule group	Activity ID format
Shakeout/Transport	Construction Step	15		
Erect/Bolt Up	Construction Step	45		
Final Torque	Construction Step	30		
QC Verification	Quality Step	10		

Cancel

Save

Add step

As a best practice:


- Use three to five steps to balance visibility with simplicity
- Define steps that can be completed within a short reporting interval (such as a week)
- Assign percentages based on level of effort, not just sequence
- Make sure all steps total 100%

Claiming schemes can also be aligned with scheduling and reporting structures through associations such as schedule groups or activity ID formats. This helps ensure that progress tracking is consistent with how work is planned and reported.

After claiming schemes are defined, they can be applied to WBS phase codes or components, depending on your project workflow. When assigned, each claiming scheme step typically inherits the quantity and unit of measure from the associated component, providing a consistent basis for tracking installed quantities across all stages of work.

3.2 CLAIMING SCHEME MANAGEMENT

From the Disciplines and claiming schemes page, you can create, assign, update, import, and export claiming schemes for construction activities and commodities. To open the Manage claiming schemes page, click Actions > **Manage claiming schemes**.




3.2.1 Create a claiming scheme

Claiming schemes can be created for both discipline and commodity construction activities, which are organized separately on the same page. New claiming schemes are created under a parent discipline or commodity to form a parent-child structure.

By default, a new claiming scheme starts with one step. You can add more steps and define how progress should be claimed across the sequence of work.

Create a claiming scheme

- 1. From the Disciplines and claiming schemes page, choose either the **Disciplines** or **Commodities** tab on the side panel.
- 2. Select the check box of the parent category for this claiming scheme. Make sure that only the parent discipline or commodity is selected.
- 3. Click the **Add** icon.



- 4. In the Name field, enter a name for the new claiming scheme.

Components > Disciplines and claiming schemes

Claiming Scheme Details Assign WBS Assign Account Code

DISCIPLINES COMMODITIES

Claiming scheme Name

Engineered Equipment
Engineering
☒ Grading
Instrumentation

Sequence	Step name	Rule type	% claiming
1	Step 1		100

5. Select **Add steps** to insert additional steps. For each step, enter the required information, such as the step name, rule type, and claiming percentage.

The total claiming percentage across all steps must equal 100%. If the total does not equal 100%, an error indicator shows and the claiming scheme cannot be saved.

Name Rough Grading

Move up Move down Add step


Sequence	Step name	Rule type	% claiming	Schedule group	Activity ID format
1	Clearing/Grubbing	Construction Step	12		
2	Stripping Topsoil	Construction Step	18		
3	Rough Grading/Bulk Earthwork	Construction Step	40		
4	Fine Grading/Shaping	Construction Step	20		
Totals:			90%		

6. When the required information is completed, click **Save**.

3.2.2 Assign claiming schemes

After you create a claiming scheme and it is ready to be used, the next step is to assign that claiming scheme. You can assign claiming schemes two different ways:

- Assign directly to a component
- Assign to a WBS phase code



To assign claiming schemes at the component level, you must assign them to each component individually. If you assign a claiming scheme at the WBS level, then every component assigned to that WBS will inherit the same claiming scheme.

3.2.2.1 Assign to a component

Claiming schemes are a required field for components. When creating a new component, select a discipline and claiming scheme on the Component Details tab.

Add activity component

CLAIMING CLAIMING HISTORY COMPONENT DETAILS

Summary

* Component name

Module 30 - E25 Beam Assembly

* Discipline

Metals

Work package ID

Select work packages

Description

* Claiming scheme

Metals

Bolted Connections

Erect Steel

Metals

Comments

[View full page](#) Cancel Save And Close Save

You can also edit an existing claiming scheme assignment for a component.


You cannot change the claiming scheme assignment on a component that has a quantity claimed against it.

3.2.2.2 Assign to a WBS phase code

When a claiming scheme is assigned to a WBS phase code, every component assigned to that WBS inherits the same claiming scheme.

As a best practice, WBS assignments should be set up prior to adding components. Any changes to WBS assignments do not override existing claiming scheme associations on components.

To enable the option to assign claiming schemes at the WBS level, make sure the toggle Associate claiming scheme to WBS phase code is set to Yes in organization or project settings.




In order to assign a WBS to a claiming scheme, the Allow As-Built setting for that WBS cost item in Control must either be set to either *All* or *Quantities*, which makes that WBS available in Plan.

Assign a WBS to a claiming scheme


- 1. From the Disciplines and claiming schemes page, Select a claiming scheme from the side panel.

You cannot assign a WBS or account code to the Contract discipline.

- 2. Open the **Assign WBS** tab.
- 3. Click **Add WBS**.



- 4. On the Add WBS slide-out panel, select the WBS phase code, and then click the **Add** icon. Use the search box as needed. You can select multiple WBS phase codes to add.




Review the selected WBS phase codes under Selected WBS.

- 5. When you are finished, click **Done**.

3.2.3 Map claiming schemes by account code

In Control, WBS phase codes are linked through mapping to account codes. Account code mapping in Plan allows you to use this relationship to assign WBS codes to claiming schemes in bulk. This option saves time when account codes are already associated to claiming schemes. This also helps improve consistency, particularly when account codes are standardized across projects.


To use this feature, you must have the Enable account code assignment to claiming scheme set to *On* in project settings.



3.2.3.3 Manage account code assignments


To make changes to account code assignments, select a claiming scheme, and then open the Assign Account Code tab.

Click **Add Account Code** to assign account codes to the claiming scheme. Click **Remove** to delete an account code assignment.



Map claiming schemes by account code

- 1. On the Disciplines and claiming schemes page, select one or more claiming schemes.
- 2. Click the **Map account code to WBS** icon.




- 3. Select **Assign all** to assign all WBS codes associated with account codes, which replaces any existing assignments.
- 4. Select **Assign all unassigned** to assign only WBS codes that are not currently linked to another claiming scheme.

A notification shows when the operation is complete.

3.2.4 Edit a claiming scheme

Existing claiming schemes can be updated from the Disciplines and claiming schemes page. To edit a claiming scheme, select it from the left panel. The image and table below show details on making edits to a claiming scheme.



Title		Description
1	Name field	Update the name of the claiming scheme.
2	Sequence	Change the order of the claiming scheme steps by updating the number in the sequence column. Alternatively, select a step and click Move up or Move down to update the order. After claim activity exists, you cannot reorder or delete steps.
3	Step details	Click within the cells to make changes to the name, rule type, claiming percent, schedule group, or activity ID format.

(continued)

Title		Description
4	Add step	Add additional claiming scheme steps.
5	Delete	Delete a claiming scheme step.

3.3 IMPORT AND EXPORT CLAIMING SCHEMES


You can import and export claiming schemes by sharing them between projects and by uploading an Excel file from the Disciplines and claiming schemes page.

3.3.1 Share claiming schemes across projects

Use this option when you want to quickly copy claiming schemes between projects without making changes to them.


Import from another project

1. In the top toolbar of the Disciplines and claiming schemes page, click the **Import** icon, and then select **Import from other project**.



2. Select a project from the list.

You can only import claiming schemes from one project at a time.




3. Click **Select**.

All the claiming schemes from the selected project are imported into your project.


Export to another project

1. To export a specific set of claiming schemes, click the check boxes to select the claiming schemes. If you want to export all claiming schemes, do not select any check boxes.
2. In the top toolbar of the Disciplines and claiming schemes page, click the **Export** icon, and then select **To other project**.



3. Select a project from the list.

4. Under Claiming schemes to send, choose **Selected claiming schemes** if you want to export a specific set of claiming schemes. Otherwise, choose **All active claiming schemes**.



5. Click **Send**.


The claiming schemes are exported to the selected project.

3.3.2 Import and export via Excel

You can import and export Excel files to help you manage claiming schemes.

Export claiming schemes

1. In the top toolbar of the Disciplines and claiming schemes page, click the **Export** icon, and then select **Data export**.



The Export history page of the Audit Log tab opens where you can view the details of the export, including the status.

Components > Export history		COMPONENTS		AUDIT LOG			Refresh export status	
Component Audit Log		File name	Sour...	Status	Total rec...	Exported by	Exporte...	
Import history		Quantity ClaimingScheme_Template_317fe253a8254c39a3e46...	Claimin...	Processing			06/05/2026	
Export history		Quantity ClaimingScheme_Template_cebefdde683e46cf893afe...	Claimin...	Complete	92		06/05/2026	
		Quantity ClaimingScheme_Template_5d40fc4f3f394549af2c1b...	Claimin...	Complete	92		06/03/2026	


2. When the status of the export is complete, click the **Download** icon to download the Excel file.

	File name	Sour...	Status
↓	Quantity ClaimingScheme_Template_317fe253a8254c39a3e46...	Claimin...	Complete
↓	Quantity ClaimingScheme_Template_cebefdde683e46cf893afe...	Claimin...	Complete
↓	Quantity ClaimingScheme_Template_5d40fc4f3f394549af2c1b...	Claimin...	Complete

3.3.2.1 Import claiming schemes

To import claiming schemes to your project, you first need to prepare an import file. To get started, export a template from Plan which includes all the necessary details.

To export a template, click the Export icon, and then select **Template**.



Open the downloaded Excel file to begin entering your claiming scheme data.

Note that the file is populated with validated data from your project. Click within a cell to see a drop-down list of options.

	A	B	C	
1	Discipline	Commodity	Claiming scheme name	Step na
2				
3	Aggregates and Paving			
4	Building			
5	Bulk Commodities			
6	Change Orders, Contract Allowances and Back charges			
7	Civil Utilities			
8	Commercial Cost			
9	Concrete			
10	Construction Equipment			
11	Contingency			
12	Deep Foundations			
13	Direct Estimated ST&S			
14	Discipline Services,Tools and Supplies			
15				
16				

To enter a claiming scheme with multiple steps, add a new row for each step of the claiming scheme. Make sure the Discipline and Claiming scheme fields are the same across steps. Use the Step sequence column to indicate the order of the claiming scheme steps.

	A	B	C	D	E	F	G
1	Discipline	Commodity	Claiming scheme name	Step name	Step %	Step sequence	Rule type
80		Valves	Valves	Step 1	100	1	
81		Wood	Wood	Step 1	100	1	
82	Metals		Bolted Connections	Stuff Bolts	40	1	Construction Step
83	Metals		Bolted Connections	Torque Bolts	50	2	Construction Step
84	Metals		Bolted Connections	QC Inspection	10	3	Quality Step
85	Metals		Erect Steel	Shakeout/Transport	15	1	Construction Step
86	Metals		Erect Steel	Erect/Bolt Up	45	2	Construction Step
87	Metals		Erect Steel	Final Torque	30	3	Construction Step
88	Metals		Erect Steel	QC Verification	10	4	Quality Step

The Import feature can be used to add new claiming schemes to your project or to make changes to existing claiming schemes. For existing claiming schemes, some details cannot be modified if the associated component has a quantity claimed against it.


3.3 Step by Step 1 – Export a claiming scheme template

You can export claiming schemes as a Microsoft Excel template, make updates outside the application, and then import the updated file to apply bulk changes.

- 1. On the Disciplines and claiming schemes page, select the **Export** icon.
- 2. Select **Template**.
- 3. Save the Excel template.
- 4. You can now use the template to update the claiming scheme data.

Import claiming schemes

- 1. In the top toolbar of the Disciplines and claiming schemes page, click the Import icon, and then select **Import file**.



- 2. Select your saved import file, and then click **Import**.
- 3. From the Audit Log tab, open the **Import history** page.

Components > Import history		COMPONENTS		AUDIT LOG			
Component Audit Log		File name	Sou...	Status	Total lin...	Errors	Total imp...
Import history		Claiming Scheme Import6_5_26_15_6_55.xlsx	Claimi...	Complete wit...	11	3	8
Export history		May_Import6_5_26_15_2_26.xlsx	Claimi...	Failed	0	0	0
		Claiming Scheme Import6_5_26_15_1_15.xlsx	Claimi...	Complete	4	0	4

- 4. Review the status of your import.
 - If the status is *Complete*, your claiming schemes have been successfully imported.
 - If the status is *Failed*, the import was unsuccessful, and you must try to import again.
 - If the status is *Complete with errors*, corrections must be made before the import can be completed.

3.3.2.2 Correcting import errors

On the Audit Log tab, a status of Complete with errors means that corrections are required before the import can be completed. Any records without errors are still imported.


The Errors column shows the number of records that could not be imported. The Total imported column shows the number of records that have been successfully imported.

Components > Import history		COMPONENTS		AUDIT LOG			
Component Audit Log		File name	Sou...	Status	Total lin...	Errors	Total imp...
Import history		Claiming Scheme Import6_5_26_15_6_55.xlsx	Claimi...	Complete wit...	11	3	8

Hover over the error indicators to view more details. Click within the cells to make changes.

> Claiming Sc...		COMPONENTS		AUDIT LOG			
< Find previous		3 errors remaining		Find next >		Import	
Discipline	Commodity	Claiming scheme N...	Step name	Step %	Step sequence	Rule type	Schedule group
☐ Routine M...		Equipment Mainte...	Inspection & Diag...	25	1		
☐ Routine M...		Equipment Mainte...	Repairs & Adjust...	15	2		
☐ Routine M...		Equipment Mainte...	Testing & Closeout	10	3		

4.1 INEIGHT PLAN WORKFLOW - COMPONENT MANAGEMENT



4.2 COMPONENT CREATION FROM SCRATCH

In this topic, you will create a new component from scratch in InEight Plan.

4.2.1 Create Components

In InEight Control, a direct cost item (WBS phase codes) has a quantity that is the sum of many components with smaller quantities which are created in InEight Plan. For example, a structural steel cost item measured in tons is made up of many pieces of steel, each with a specific weight (in tons). When claiming work complete, you could calculate the weight of each piece of steel installed and claim that much at the WBS level.

- *If you did this, how would you know what work is complete and what specific work is remaining?*
- *What have you already claimed and what have you not?*

- *What if a Foreman doesn't have the time to weigh each piece of steel before installing, or what if he weighs incorrectly?*

Components allow you to break down the WBS quantity into smaller, more manageable sub items for claiming. When you claim components, you can easily see what specific items have been completed and what is remaining. You do not have to guess at what has already been claimed to date. Foremen do not need to do any calculating in the field; they simply report the components they completed. Components already have an assigned quantity based on takeoff calculations.

- *Can you think of how components would help claiming of other disciplines like Pipe, Electrical, or Concrete?*
- *How are these disciplines measured vs how is the work performed?*

Components aim to bridge that gap.

4.2.2 Types of Components

There are several types of components in the Quantity Tracking module:

- Activity
- Material
- Assembly
- Contract

You can create activity, material, and assembly components directly in Plan. Contract components can only be created indirectly from InEight Contract.

These different types let you claim procurement activities and construction activities separately. To do this, material cost and labor cost must be broken out in separate WBS codes. If that is the case, you can add the same steel components as activity components and material components as pictured below:

Components								
Actions      								
	Name ↑	Parent record	Assembly	Type	Discipline / Commod...	Claiming sc...	WBS	Description
☐	Module 01 - A23: C...	Cross brace assem...	Cross brace assem...	Material	Steel	Steel	1087	
☐	Module 01 - A23: C...	Module 01 - A23: C...	Cross brace assem...	Activity	Metals	Erect Steel - L...	1005	Module 1 - A2...

When you create components for both the material and activity, you can then earn hours based on a unit rate for the activity, and earn dollars based on material unit cost for the material and assign them to two separate WBS codes.

Component types are shown with different color schemes:

- Activity: Blue
- Material: Gray
- Contract: Metallic purple
- Assembly: Forest green

4.2.2.1 Assembly Components

You can combine activity and material components into assembly components. An assembly allows claiming to roll up into one parent record.

For example, if you are building a wall using 2x4s, you might have the following components:

- Material of 2x4s
- Activity of cutting 2x4s to lengths from rough cut
- Activity of labor to assemble 2x4s into wall

If you create a new assembly component to build a 2x4 wall, you can set the parent record of the material and labor activities to be the assembly. If you set the parent record of the cutting activity to be the material, the cutting activity also becomes part of the assembly. Using assembly components and parent records lets you create hierarchies of components so that claiming rolls up into one record. The new Assembly column shows which assembly each component belongs to.

When you edit an assembly or material component, you can use the Related Components tab in the slide-out panel to associate existing components. Only associated components lower in the hierarchy are shown.

You can only add associations from the Related Components tab. To remove an association, you must edit the Parent record field of the associated component.

Components

Actions

	Name	Parent record	Assembly	Type
☐	Assembly of build 2x4 wall		Assembly of build 2x4 wall	Assembly
☐	Material of 2x4's	Assembly of build 2x4 wall	Assembly of build 2x4 wall	Material
☐	Activity for labor to assembly 2x4's into wall	Assembly of build 2x4 wall	Assembly of build 2x4 wall	Activity
☐	Activity to cut 2x4's to length from rough cut	Material of 2x4's	Assembly of build 2x4 wall	Activity

4.2.2.2 Contract Components

Contract components cannot be created directly in Plan. A Schedule of Values (SOV) item from Contract automatically becomes a contract component in Plan if the SOV is not set to hide in Plan and Progress.

In Quantity tracking, a contract component's basic details from Contract cannot be edited. You can associate a contract component to an assembly.

You can assign a contract component to a claiming scheme by adding a claiming scheme to the Contract discipline in Actions > **Manage claiming schemes**. You can then edit a contract component to change the claiming scheme. A contract component can only be in the Contract discipline. See Claiming Scheme Creation for more information on how to add a claiming scheme.

4.2.3 Methods of Creating Components

There are four methods for creating activity, material, and assembly components:

Component Creation	
From Scratch	Create each component manually using the new component slide out panel.
Import Template	Import multiple components into InEight Plan simultaneously.
Copy	Create one new component from an existing component.
Split	Create multiple new components from an existing component.

4.2.4 Component Attributes


When creating components, a number of fields called attributes are available to be filled out. It is not necessary to fill out every single field, but the more information input, the better. Attributes help make tracking components easier. In many cases, depending on the size of the job, you may have hundreds of thousands of components. In such a case, it can be difficult at times to distinguish the differences between components if only a few attributes are filled out.

4.2.4.3 Validated Fields

You will rely heavily on certain component attributes for reporting purposes. For these attributes, it is important that data integrity is maintained.

For example, the area and system fields are commonly used for reporting. For these fields, it is important that the area and system entered are always spelled and formatted exactly the same way every time. Imagine a scenario where the data entered for the area field is spelled and formatted five different ways by five different users. In this case, when a report is run for areas, the report will only identify the data that is spelled and formatted one of the five ways. All data for the other four will be left out and your report will be missing crucial information.

To solve this problem, validated fields are used. Validated fields are simply a pre-defined list of values that populate into a drop-down menu. Instead of making these fields free text fields, a drop-down list is utilized. This drop-down list is maintained in the Configure CWA and project values page. You access the Configure CWA and project values page from the Actions menu on the Components page in Quantity tracking.



4.2.4.4 Location

In the Location section of the Configure CWA and Project Values page, you can add a construction areas, construction segments, and commodities as data validated tag values to assign to components. Examples of construction areas are North and South. An example of a construction segment is Phase 1. Examples of commodities are rebar and steel. These can then be used to map your components for reporting.

Depending on how your project is set up, if you assign a component to a work area in Work packaging, the component's location is updated to match the work area and cannot be edited in Quantity tracking. The setting that controls this behavior is called Automatically inherit CWA to component from assigned work package.

The screenshot shows the 'Configure CWA and project values' page with the 'LOCATION' tab selected. It features two main sections: 'Construction area' and 'Construction Segment'. Each section has a table with columns for Position, ID, Description, and Note. The 'Construction area' table has 4 rows with positions 1-4 and descriptions North, South, East, and West. The 'Construction Segment' table has 2 rows with positions 1-2 and descriptions Phase 1 and Phase 2. Both tables have a vertical scrollbar on the right. At the bottom of each table is an 'Import to [section name]' button. There are also 'Export' buttons at the bottom of each section.

4.2.4.5 Engineering

In the Engineering section of the Configure CWA and Project Values page, you can associate turnover packages and systems of work such as fire, water, or sprinkler to a component. You can further define subsystems for a component. Depending on your permissions, you might not be able to edit component attributes, which are typically maintained by an administrator. If you need the drop-down list for a validated field update and do not have access, contact your system administrator.

The screenshot shows the 'Configure CWA and project values' page with the 'ENGINEERING' tab selected. It features two main sections: 'Turnover' and 'System'. Each section has a table with columns for Position, ID, and Description. The 'Turnover' table is empty with a note 'No records available'. The 'System' table has 3 rows with positions 1-3 and descriptions FND, GEN, and SST. Both tables have a vertical scrollbar on the right. There are also 'Import to [section name]' buttons at the bottom of each section.

The Engineering section in the Edit activity component > **Component Details** tab also lets you link InEight Design data to a plan component. You can enter or update the turnover complete date, test package, complete date, and owner code.

✕

0.00%

Edit activity component

CLAIMING

CLAIMING HISTORY

COMPONENT DETAILS

Summary

Location

Specifications

Procurement

Project Values

Discipline Specific

Engineering

Turnover complete date

Test package

Complete date

Owner code

Linked EWP

None

Schedule

<

>

View full page

Cancel

Save and close

Save

4.2.4.6 Using Component Attributes

On the Quantity tracking Components page, you can add the component attribute columns to your view. Clicking into a field under one of the component attribute columns provides the drop-down values for the attribute as defined previously on the Configure CWA and Project values page.

Components

Actions

Filter: (select one)

Minus icon

Filter icon

Group icon

Link icon

Save claim...


View:

	Name ↑	Parent record	Assembly	Type	Discipline / Commo...	Claiming sc...	WBS	Const area	System	Turnover	Tur
☒	Module 01 - A23: Cr...	Cross brace assem...	Cross brace assem...	Material	Steel	Steel	1087		None		
☐	Module 01 - A23: C...	Module 01 - A23: C...	Cross brace assem...	Activity	Metals	Erect Steel - L...	1005	North			
☐	Module 01 - A24: C...			Activity	Metals	Erect Steel - L...	1005	North			
☐	Module 01 - A6 Co...			Activity	Metals	Bolted Conne...	1006	North			
☐	Module 01 - A7 Co...			Activity	Metals	Bolted Conne...	1006	North			
☐	Module 01 - B23: C...			Activity	Metals	Erect Steel - L...	1005	North			
☐	Module 01 - B24: C...			Activity	Metals	Erect Steel - L...	1005	North			

4.2.4.7 Split Contract Components


You can split a contract component into new smaller components. In Quantity tracking you can select a single component, and then click the Split component icon. The Split component dialog box opens. You can split the original component to up to 50 new components. You can apply quantity to the new components. The original component (line 1 in the split component window) will have its quantity reduced.

The original component cannot be set to a value less than zero. If all the quantities are associated to the split components, then the lowest value the original component can be set to is zero.




4.2.4.8 Validated lists in Field attributes

The Field attributes drop-down list is found under the Discipline Specific section of the Edit activity components dialog box.




To create the validated lists, go to Platform> Master data libraries> **Attributes** and then click the **Add attribute** icon. The Add attribute dialog box opens, enter the attribute information. In the Type field, select **Validated list**. After you save the attribute, it shows on the Field attributes page.




4.2.4.9 Schedule Components

The Schedule section in Edit activity component > **Component Details** tab lets you manage schedule details directly from an activity component. You can enter or update the Activity ID, Activity name, Planned start date, and Planned end date of a schedule. You can enter free-form text or search existing data. If an existing Activity ID is selected, all other fields are populated with any data from InEight XER imports. The Do not schedule check box integrates information from InEight Design.



4.2.4.10 Project Values

Assigned project value types are created in the master data library, they can be linked to a project, which then lists the project values in quantity tracking. Go to Quantity Tracking > Column chooser to add the project values to your grid view.




Overview - New Component Slide Out Panel

Title		Description
1	Summary Menu	Contains general high-level component information such as Name, WBS, Quantity, Unit of Measure, and Discipline.
2	Location Menu	Contains exact location information of the component such as Building, Elevation, Construction area, and System.
3	Specifications Menu	Contains information regarding exact specification for the component such as: Size, Weight, Thickness, Material code, and External link.
4	Procurement Menu	Contains information regarding the procurement of the component such as Supplier, PO #, and Shop/Field. This section also shows related contract information for contract components..
5	Discipline Specific Menu	Contains information that is specific to the discipline selected in the summary menu. This is different for every discipline.
6	Engineering	Contains information regarding the engineering of the component such as Turnover, Test Package, and Owner Code.

Overview - New Component Slide Out Panel (continued)

Title		Description
7	Claiming Scheme Menu	Shows the claiming scheme selected in the summary menu.
8	Claiming History	Shows a log of what has been claimed to date for this component and by whom.
9	View Full Page Link	Opens the slide-out panel into a separate window and expands all menus. Allows for scrolling through the menus instead of opening accordions individually.
10	% Complete Field	Shows overall percent complete of the component.




4.2.5 Component Creation


The following step by step walks you through how to create a component from scratch.

Create a Component from Scratch

- 1. From an open project, go to the **Quantity Tracking** module.
- 2. To create a component, select the **Add** icon on the left toolbar.



3. Select **Activity**.



- This opens the new activity component slide out-panel. By default, the summary accordion menu should be expanded
4. In the Summary menu, enter your component details.

Add activity component

CLAIMING CLAIMING HISTORY **COMPONENT DETAILS**

Summary

Component name

WBS Component quantity Unit of measure Schedule ID

WBS forecast QTY WBS planned QTY WBS to date QTY % WBS QTY complete

Discipline Claiming scheme Work package ID

Parent material

Description Comments

Location

Specifications

Procurement

Depending on what project setting you have set up, when you assign your WBS, the Unit of Measure, Discipline, and Discipline/Claiming Scheme fields might be automatically populated and locked for editing.

You can associate material components and assembly components to activity components by adding materials or assemblies to the Parent record field. To associate materials, check that you have the setting Associate Claiming to Material Components turned on in your Project Settings > **Plan Quantity Tracking**.

5. Open the Location menu by clicking on the **Location** title header.
6. In the Location menu, enter the location and commodity information.
7. Open the **Discipline specific** menu and enter your grade and coating information.

Add activity component

CLAIMING

CLAIMING HISTORY

COMPONENT DETAILS

Summary

Location

Specifications

Procurement

Discipline Specific

AUX 1

AUX 2

AUX 3

AUX 4

AUX 5

Coating

Engineer Responsible

Foundation Drawing

Grade

Height

Length

Sequence

Structure Drawing

Tons

Torque Value

Total Pieces

Vendor Drawing

Width

A992

GALV

Engineering

View full page

Cancel

Save and close

Save

8. After you have completed filling out your information, click **Save**.

The following Step by Step walks you through how to create a component by copying an existing component.

Copy an Existing Component

1. Select a component.

The Copy function only works when you select a single component.

2. Click the **Copy** icon in the upper-left of the page.

The Copy component dialog box opens

3. Enter a name for the new component.

The default name adds -copy to the end of the original component's name

4. Click **Copy**.

The following Step by Step walks you through how to create multiple components by splitting an existing component.

Split an Existing Component

1. Select a component.

The Split function only works when you select a single component.

2. Click the **Split** icon in the upper-left of the page.

The Split component dialog box opens

3. Click the **Add** icon next to Split components to increase the number of new components to split the original into.

To remove a split component, click the **Remove** icon next to the component.

4. Enter names for the split components.

The default names add -n to the end of the original component's name, where n is an increasing number starting at 1

5. Change the Quantity for each of the split components.
6. Click **Split**.

The following Step by Step walks you through how to edit multiple components at the same time.

Bulk Edit Components

1. Select multiple components.

You can edit a maximum of 50 components at the same time.

2. Click the **Bulk edit** icon in the upper-left of the page.
 - The Bulk edit dialog box shows
3. In the dialog box, select a column and enter a new value for the column.
4. Add or remove additional columns as necessary, and then click **Save**.

You can edit a maximum of five columns at the same time.

The Bulk delete components option in the Actions menu lets you delete up to 500 components at a time. The components must have zero claimed quantity to be deleted. Components with installed quantity are never deleted, so only the first 500 zero-quantity components can be deleted. To help target specific components, bulk delete will work when filters are applied and only values with the selected filters will be deleted.

The following Step by Step walks you through how to delete components with zero claimed quantity in bulk.

4.2 Step by Step 1 – Bulk Delete Components

1. Open the **Actions** drop-down menu, and then select **Bulk Delete Components**.

A warning dialog box opens.
2. Select the confirmation check box.
3. Click **Delete**.

4.3 COMPONENT CREATION FROM IMPORT

In this topic, you will learn how to upload multiple components at once via the Import Template.

Scenario

Imagine you are the structural steel field engineer responsible for tracking all steel erection for your module. You receive a bill of materials from your steel fabricator that matches the erection drawings. The bill of materials has all the information you need to input for components - piecemarks, weight, grade, coating, etc. You need to add all the piecemarks as components, so you can track them as they are installed.

4.3.1 Import Template

You often receive lists of components from an outside source.

Can you think of other examples?

- *Electrical cable or termination schedules*
- *Pipe spool fabricator bill of materials*
- *Mechanical equipment list*
- *Take off sheets from estimators*

In these situations, it saves time to import multiple items at once. This can be done using the export and import feature in Plan.

The Import Template is a Microsoft Excel spreadsheet used to upload multiple components into Plan at once. The import template is generated first by setting up your view to show the columns of information you want to import, in addition to any required columns. Then you export the import template to Excel. You can export with or without data (by choosing Data Export), as well as, Excel equations. This means you can export just the column headers or all the information in the cells below as well. After export, you can fill in your information in the spreadsheet, save it, and import it. You have the option to import only new items or overwrite information on existing items (based on unique component IDs).

Component IDs are distinct from component names. You can have components with the same name, but they must have unique IDs. To change a component name, you must first know the component ID. This ID is used as the key reference point for all components. To find the component ID, from Quantity tracking in standard grid view, click the **Export** icon, and then select **Data export**. The Microsoft Excel file shows the component IDs in column A.

After import, Plan checks the file for any errors. Errors might include:

- Validated fields that don't exist
- WBS codes that are not available
- Non-unique component IDs

A report is generated to help you find and correct any errors before continuing the import.


The following step by step walks you through how to export the Import Template, populate it, and upload it back into Plan.

Component IDs must be unique within the same type of component (activity, material, or assembly). You cannot have two components of the same type with the exact same ID, but you can have an activity component with the same ID as a material component. If you want to duplicate an existing component (such as, the component created manually in the previous section), you must either delete it, or change the ID of either the existing or imported component.


Required columns are exported even if you hide them.

Create Components from Excel Import


1. From an open project, go to the **Quantity Tracking** module.



2. In Standard View, select the **Column Chooser** on the far right of the column header row.



3. From the Column Chooser dialog box, select columns from the **Available columns** list, and then use the **right arrow** to move them into the **Selected columns** list. Save your columns.



4. Click the **Export** icon on the toolbar.

View:

Save claim...

WBS to date ...	% WBS QTY ...	Work packag...	Const area	System	Turnover
0.15000	6.01685		South		
			South		
			South		

5. Select **Template**.

View:

Save claim...

...	Work pac	Template	System	Turnover
		Data export		

- A Microsoft Excel spreadsheet automatically opens or is shown at the bottom of your screen to download

6. Click the drop-down arrow for the file, and then select **Open**.

☐	Module 11 - A7 Co...	1006	Activity	Metals
☐	Module 11 - A6 Co...			als
☐	Module 10 - A7 Co...			als

© 2020 InEight Inc. [Privacy and](#)

Light Component I....xl...

Open

Always open files of this type

Show in folder

Cancel

- The resulting spreadsheet is now your Import Template and contains all required columns and only the optional columns that were shown in Plan at the time of exporting


	A	B	C	D	E	F	G
1	English	User Selected Language					
2	REQUIRED	Field is required for import					
3	OPTIONAL	Field is optional for import					
4	VALIDATED	Field must match master data available in application					
5	IGNORED	Field not to be populated					
6	DS/CS	Discipline/Commodity specific fields					
Note:							
1. If the Project configuration allows associating Claiming scheme to WBS, then specifying Discipline/Commodity is not mandatory in presence of WBS. Discipline or Commodity will be identified based on Type							
2. Columns with data type Text should be formatted as Text to see trailing zeros after decimal.							
8	Name	Parent record	Assembly	Type	Discipline/Commodity	Claiming Scheme	WBS
9	Text	Text		Text	Text	Text	Text
10	200	200		10	100	100	50
11							250

7. In the Name column, enter your component name.

8. Enter the component Name data.

	A	B	C	D	E	F	G	H
1	English	User Selected Language						
2	REQUIRED	Field is required for import						
3	OPTIONAL	Field is optional for import						
4	VALIDATED	Field must match master data available in application						
5	IGNORED	Field not to be populated						
6	DS/CS	Discipline/Commodity specific fields						
Note:								
1. If the Project configuration allows associating Claiming scheme to WBS, then specifying Discipline/Commodity is not mandatory in presence of WBS. Discipline or Commodity will be identified based on Type								
2. Columns with data type Text should be formatted as Text to see trailing zeros after decimal.								
8	Name	Parent record	Assembly	Type	Discipline/Commodity	Claiming Scheme	WBS	Description
9	Text	Text		Text	Text	Text	Text	Text
10	200	200		10	100	100	50	250
11	Module XXX - A6: Column Assembly			Activity	Metals		1074	Copy Name column

9. **Save** the file to your desktop, so you can easily find it.



10. Return to Plan, and then click the **Import** button on the right toolbar.

View:

Save claim...

WBS to date ...	% WBS QTY ...	Work packag...	Const area	System	Turnover
0.15000	6.01685		South		
			South		
			South		

- An Import data dialog box is shown

11. Select **Browse**.
12. From the resulting Open window, locate and select your file, and then select **Open**.
13. Select **Add new items only**.

Plan - Google Chrome

Import data from template

The data will be imported into Components

Drag and drop the file here or browse

Browse...

☒ Add new items only

☐ Add new items and update existing


☐ Email me upon completion

Cancel

Import

By selecting **Add new items only**, the system will flag an error if you’ve accidentally created a component with the same ID as a previously created component. If you select Add new items and update existing, instead of flagging an error for a component ID that already exists, the system overwrites the data for that component.

14. Click the **check box** for Email me upon completion.



- This alerts you to the completion of the upload


15. Click **Import**.

- The import file is added to the import queue
- To see all your import files and their statuses, click **View file import queue**

You can continue working in the application while your imports are processed. A notification tells you if your file is imported successfully or not.

If you have an error, check that the ID of your component is not the same as an existing component.

16. Click **Close**.



Scenario Recap

Now you can see how easy it is to upload multiple components. Picture a project with thousands of components from multiple sources that can be combined on an import template and easily loaded in quickly.

4.4 COMPONENT AUDIT LOG

This topic describes the Component audit log and how to use it.

4.4.1 Summary

The Component audit log lets you track changes made to components and in which systems the changes are made. The Audit log also lets you review Import and export history. To open the audit log from the Components list, select the Audit Log tab.

Steel Structure Training Job 105091 / Plan / Quantity tracking										
Components	AUDIT LOG									
	Last 30 Days									
Component Audit Log	Component ID	Component name	Description	WBS	Source	Attribute	Value before	Value after	Changed by	Changed on
Import history										
Export history										

The following table describes the different parts of the audit log.

Overview - Component Audit Log

Title		Description
1	Date range	Adjust the date range of data to be shown. You can choose from standard ranges or a custom range.
2	Export	Export a filtered view of the audit log.
3	Row density	Adjust how close together rows are shown.
4	Grid	Shows each change organized by columns, which can be filtered and sorted.

The screenshot shows the 'Component Audit Log' interface. Callout 1 points to the 'Last 30 Days' date range selector. Callout 2 points to the 'Export' button. Callout 3 points to the row density controls (10, 20, 50, 100, 200, 500, 1000). Callout 4 points to the main data grid. The grid has columns: Component ID, Component name, Description, WBS, Source, Attribute, Value before, Value after, Changed by, and Changed on. The data shows multiple rows for 'Maintain Env. Controls - D1' with various attributes like 'ToDateQuantity' and 'InstallQuantity1'.

Component ID	Component name	Description	WBS	Source	Attribute	Value before	Value after	Changed by	Changed on
2924433	Maintain Env. Controls - D1	D1 - Env Controls	1017	Claiming	ToDateQuantity	10.00000	12.00000		02/04/2022
2924433	Maintain Env. Controls - D1	D1 - Env Controls	1017	Claiming	InstallQuantity1	10.00000	12.00000		02/04/2022
2924433	Maintain Env. Controls - D1	D1 - Env Controls	1017	Claiming	ToDateQuantity	10.00000	10.00000		02/04/2022
2924433	Maintain Env. Controls - D1	D1 - Env Controls	1017	Claiming	InstallQuantity1		10.00000		02/04/2022
2924433	Maintain Env. Controls - D1	D1 - Env Controls	1017	Claiming	ToDateQuantity	70.00000			02/04/2022
2924433	Maintain Env. Controls - D1	D1 - Env Controls	1017	Claiming	InstallQuantity1	70.00000			02/04/2022
2924433	Maintain Env. Controls - D1	D1 - Env Controls	1017	Claiming	ToDateQuantity	44.00000	70.00000		02/04/2022
2924433	Maintain Env. Controls - D1	D1 - Env Controls	1017	Claiming	InstallQuantity1	44.00000	70.00000		02/04/2022

Displayed results: 8

4.4.2 Component Export History

The Export history log in Quantity Tracking lets you track the component export history.

To view the Export history in the audit log, select **Export history** from the left navigation menu.

The screenshot shows the 'Export history' log interface. The top navigation bar includes 'Components' and 'Export history'. The main table has columns: Component Audit Log, File name, Source, Status, Total record count, Exported by, and Exported on. The 'Export history' row is highlighted. A 'Refresh export status' button is visible in the top right corner.

Component Audit Log	File name	Source	Status	Total record count	Exported by	Exported on
Import history						
Export history						

You can download previous component history logs and see who exported them.

To download, click the **Download** icon,

Steel Structure Training Job | 105091 / Plan / Quantity tracking

COMPONENTS

AUDIT LOG

Component Audit Log

Import history

Export history

File name

Source

Status

Total record count

Exported by

Exported on

Quantity Component_Template_3d3f439aa8824db5bcadff25681ac62b_03192026042232.xlsx

Component

Complete

442

lake.mallatt

03/19/2026

Quantity Component_Template_761df119eb354410b804466b08a61b01_03192026015524.xlsx

Component

Complete

1

lake.mallatt

03/19/2026

Quantity Component_Template_38bf0f9-6af1-4a35-a0e9-987a0d2fe1cf_12182025051338.xlsx

Component

Complete

420

lake.mallatt

12/18/2025

Quantity Component_Template_3c46988b-1a6b-4e28-a30b-d42cfe5bca1_10152025074337.xlsx

Component

Complete

437

Laurea Koonen

10/15/2025

The export is a Microsoft Excel file with an unlimited component export count.

Longer record counts will result in a longer download time but, this is unlimited.

When exporting previous version history from yourself or other users, you can also undo changes.

1	English	User Selected Language							
2	REQUIRED	Field is required for import							
3	OPTIONAL	Field is optional for import							
4	VALIDATED	Field must match master data available in application							
5	IGNORED	Field not to be populated							
6	DS/CS	Discipline/Commodity specific fields							
7	Note:1. If the Project configuration allows associating Claiming scheme to WBS, then specifying Discipline/Commodity is not								
8	Component id	Name	Parent record	Assembly	Type	Discipline/Commodity	Claiming Scheme	WBS	Planned start date
9	Numeric	Text	Text		Text	Text	Text	Text	Date: MM/DD/YYYY
10		200			10	100	100	50	10
11	6530738	001ga Manhole Ground Rods			Activity	Electrical	# Underground Grounding-90/10	3983	
12	5075640	1009 - Break/LO Asphalt Paving - Substation			Activity	Removals and Demolition	1009 - Break/LO Asphalt Paving - TO 1008		
13	5045014	1009 - Break/LO Asphalt Paving - TO			Activity	Removals and Demolition	1009 - Break/LO Asphalt Paving - TO 1009		

4.4.3 Considerations

- By default, the audit log shows the last 24 hours of changes made to components.
- Changes shown in the log depend on your permissions.

4.5 DEFAULT COMPONENTS

This topic describes default components and how they can be used in quantity tracking.

4.5.1 What are Default Components?

Default components are linked by WBS to cost items in InEight Control. Default components are automatically added to quantity tracking depending on organization and project settings for Plan and cost item properties in Control. Default components can also be used in InEight Progress.

Default components are useful to claim quantities against directly and as points of reference to create your own components that replace or supplement the defaults.

Many properties of a default component are brought in from the cost item in Control. For example, a default component's discipline or commodity and claiming scheme are set to WBS. These values are system generated and help you distinguish default components from user-created components.

A cost item from Control can be a default component depending on the following properties in Control:

- Allow as-built field - Values can be None, All, Quantities, or Costs. However, if this field is set to None or Costs, the default component cannot be claimed against in quantity tracking.
- As-built lock - If this check box is selected, the default component cannot be claimed against in quantity tracking.
- Hide in Plan/Progress - Do not select this check box.

If you add a new component with the same WBS, the default component is removed unless it has already been claimed against. If the default already has claiming, its remaining claiming value is reduced to the amount already claimed. Removed default components are still shown in reporting of inactive components and audit logs of claiming if the default component had claiming against it.

All default components are activity components.

4.5.2 Enable and Refresh Default Components

Default component settings are located in Settings > **Plan**, in the General section. You can turn default component creation on or off at both the organization and project levels. At the project level, you can refresh the list of default components, which is useful when you turn default component creation on after it has been off for some time.

4.5.2.1 Considerations for Enabling Default Components

Before you decide to enable, disable, or refresh default components, consider the following conditions.

If default component creation is:

- On at the organization level:
 - You cannot turn it off at the project level.
- On at any level:
 - If you refresh default components, quantity tracking's list of default components is updated. New default components might be created if their associated WBSs were added in InEight Control while default component creation was switched to *Off*.
 - You do not have to click Refresh every time a change is made to a cost item in Control. If the toggle is *On*, default components in quantity tracking show current data from Control.
- Off at the organization level:
 - You can adjust the setting at the project level as necessary.
- Off at the project level:
 - If you create components associated with WBSs, those components can still send claiming data to Control.
 - If you refresh default components after the setting was previously on, all default components without claiming are removed from quantity tracking.


The following step by step explains how to turn on default component creation for an organization, and then refresh a specific project's default components.

4.5 Step by Step 1 – Enable and Refresh Default Components


1. At the organization level, go to Settings > **Plan**.
2. In the General section, turn on **Enable default component creation**, and then click **Save**.
3. At the project level, go to Settings > **Plan**.
4. In the General section, click **Refresh**, and then click **Save**.

4.5.2.2 Delete default components

In Quantity Tracking, you can delete a default component. Select your component and then click the Delete icon to delete the default component.




At the project level under the global options, you can restore the deleted default components by clicking **Refresh**. When you use this option, you will enable all default components.



This page intentionally left blank.

5.1 INEIGHT PLAN WORKFLOW - QUANTITY CLAIMING



5.2 QUANTITY CLAIMING

This topic covers how to claim component quantities in the InEight Plan application.

5.2.1 Process for claiming quantities

Quantities can be claimed in Control, Plan or Progress. There are reasons to claim in each of the different modules, but this lesson will focus on claiming in Plan. Since labor and material are expensed in the field, quantity for activities and materials can be claimed during the daily planning process of InEight Progress. This allows foremen to select (not calculate) the work they completed during the shift while filling out the time sheet at the end of the day, and it is reviewed by field engineers or superintendents before final quantities are approved. Sometimes, claiming in this fashion is not accurate and what was originally claimed needs to be revised. To manage claiming quantities without

having to create daily plans, it is important to understand how to use the Quantity Tracking module of Plan.

5.2.2 Why claim at a component level?

Claiming directly in the Quantity Tracking module of Plan is different than claiming in the Control module. In Quantity tracking, claims are made at the component level. This is more specific than claiming in Control at the WBS level. For example, suppose a WBS cost item has a quantity of 200 tons of steel. If 20 tons are erected so far, how would you know which specific pieces make up that 20 tons? How could you audit this claiming?

Direct labor and material codes should be claimed at the component level in the interest of transparency. Completed component quantities roll up into the WBS completed quantity. To enable quantities to be claimed in Plan, the cost item must have the Hide in Plan/Progress box unchecked within InEight Control and at least one component for that cost item must exist in Plan.

If two users concurrently are trying to claim quantities for the same component, the following error message will prompt them to refresh the page.



Unable to update components

The component claiming details have changed. The page must be reloaded.

Reload page


5.2.3 Claiming in the Standard Grid View

In the following Step by Step you will claim quantities in the Standard Grid view via the Edit component slide out panel.

Claiming is ideally done in the data block view, which lets you focus on only the information needed for claiming.

Quantity Claiming (Standard Grid View)

- 1. Navigate to the **Quantity Tracking page** and select the **View As button** to see your workspace in Standard Grid view.
- 2. Find and select the **check box** to the left of the component you previously created.
- 3. Click on the **Edit icon** to open the component editor slide out panel.



- 4. On the Claiming tab, check the box in the **Complete** column for step one.
- 5. Enter an Executor and Approver.

Edit activity component

CLAIMING

CLAIMING HISTORY

COMPONENT DETAILS

Step	% Cl...	Com...	Date	Quantity	Install qty	This perio...	UoM	Qty joi...
Shakeout/Trans	15	☒	03/17/2020	2.49300	2.49300	2.49300	Ton	☒
Erect/Bolt Up	45	☐		2.49300	0.00000	0.00000	Ton	☒
Final Torque	30	☐		2.49300	0.00000	0.00000	Ton	☒
Quantity Verific	10	☐		2.49300	0.00000	0.00000	Ton	☒

2.49300

Approver

Executor

Notes

Cancel

Save and close

Save

6. At the bottom of the slide out panel, click **Save**.

Select **Save** to have claimed quantities be added/deducted from your percent complete or to show up in your claiming history report.

- Notice that the percentage indicator in your component view has changed

Edit activity component

CLAIMING CLAIMING HISTORY COMPONENT DETAILS

Step	% Cl...	Com...	Date	Quantity	Install qty	This perio...	UoM	Qty joi...
Shakeout/Transp	15	☒	03/17/2020	2.49300	2.49300	0.00000	Ton	☒
Erect/Bolt Up	45	☐		2.49300	0.00000	0.00000	Ton	☒
Final Torque	30	☐		2.49300	0.00000	0.00000	Ton	☒

15%

You can also claim a portion of the quantity for a single step by inputting the quantity in the **This Period** cell.

Edit activity component

CLAIMING CLAIMING HISTORY COMPONENT DETAILS


Step	% Cla...	Com...	Date	Quantity	Install qty	This period...	UoM
Shakeout/Transp	15	☒	10/31/2018	2.49300	2.49300	0.00000	Ton
Erect/Bolt Up	45	☐	10/31/2018	2.49300	1.00000	1.00000	Ton
Final Torque	30	☐		2.49300	0.00000	0.00000	Ton
QC Verification	10	☐		2.49300	0.00000	0.00000	Ton

15%


To claim in the Plan Quantity Tracking module, the component WBS must have **Allow-As-Built** set to **All** or **Quantities** in InEight Control. See your Control Manager to verify this setting if unable to claim the component. The same scenario follows for claiming in data blocks.

5.2.4 Over claim component quantity

With the applicable permissions, you can overclaim component quantity using the Allow overclaiming of components toggle.



When the component is claimed over 100%, the toggle is locked in the Global options.



When the component is complete, the % complete is set to 100.

Step name [1]	Step % [1]	Com...	Quantity [1]	Installed qty [1]	This period qt...	UoM [1]	Date [1]	Executor [1]
Step 1	100	☒	2.00000	2.00000	0.00000	Ea	12/05/2022	
Step 1	100	☒	1.00000	1.00000	0.00000	Ea	12/05/2022	
Step 1	100	☐	9.00000		0.00000	Ea		
Step 1 - new t...	100	☐	0.00000	0.00000	0.00000			
Step 1 - new t...	100	☒	4.00000	4	-2.00000		12/07/2022	

5.2.5 Claiming in the Data Blocks View

In the following Step by Step you will claim quantities in the Data Blocks view.

Quantity Claiming (Data Blocks View)

1. Navigate to the **Quantity Tracking** page and select **View As button** to see your workspace in Data Blocks view.
2. Turn on the **[your name] filter** that you created in Quantity Tracking *Lesson 2 – General Navigation* using the filter drop-down menu on the right toolbar.
3. Select the check box in the Complete column of the Step 1 data block for three of the components in your module.

If the Step 1 data block is not shown, click **Manage step columns**, and then select the step in the dialog box.

4. Click the **Save** button in the upper right of the page.

You can also claim using percentage complete or to-date installed quantity at the component step level.

In data block view, there is an Apply installed quantity to all button at the top of each Step data block. You can use this button to apply an installed quantity to all components in your current view.

You can only apply installed quantity up to 50 components at a time, so you must filter your view first to show only the components you want to apply the installed quantity to.

The following Step by Step shows you how to apply an installed quantity to multiple components.

5.2 Step by Step 1 – Apply Installed Quantity to All

1. Filter your view to show only the components you want to apply an installed quantity to.
2. Click **Apply installed quantity to all**.
3. Enter the install date.

The screenshot shows a modal dialog titled "Apply installed quantity to all". On the left is a table with the header "Installed qty" and five rows, each with the value "0.00000". On the right, there is a date picker for "Install date" set to "11/22/2021". Below the date picker are two radio button options: "Step JTD installed qty" (which is selected) and "Step JTD % complete". Each option has a corresponding input field. At the bottom of the dialog are "Cancel" and "Apply" buttons.

4. Select either the quantity or percentage options.
5. Enter a quantity or percentage in the field.

If you apply a certain amount that exceeds a component's remaining quantity, all the remaining quantity is installed.

6. Click **Apply**.

The changes are flagged as pending in each row.

7. Click **Save claiming**.

You have now claimed multiple items as complete by using the Data Block view. You can use the Standard Grid view and bring in columns for each claiming step to claim in that view also. Some setup is required for this option.

5.3 EDIT CLAIMED QUANTITIES

This topic covers how to edit the claimed quantity of a component in the InEight Plan application.

It is possible that you may need to update the quantity that has been claimed for a component. You might find the need to:

- Claim more quantity for a step in a specific component
- Back out quantity that was reported incorrectly

5.3.1 Quantity Joined

In Quantity Tracking, when the quantity joined box is unchecked for a step in the claiming scheme, the step quantity and the component quantity are no longer connected. Any updates made to the component quantity will not be reflected for that step. You can re-join step quantities with the component quantity.

ClaimingSchemes ^										
Step	% Cla...	Com...	Date	Quantity	Install qty	This period...	UoM	Executor	Approver	Qty joined
Assemble	25	☐		5.00000	0.00000	0.00000	LF			☐
Erect	25	☐		10.00000	0.00000	0.00000	LF			☐
Detail	40	☐		5.00000	0.00000	0.00000	LF			☐
Verification & Do	10	☐		1.00000	0.00000	0.00000	LF			☐

You can re-join step quantities with the component quantity. By checking the re-join box, the step quantity is linked again to the component quantity, so when the component quantity is changed, the step quantity will automatically change along with it.

ClaimingSchemes ^										
Step	% Cla...	Com...	Date	Quantity	Install qty	This period...	UoM	Executor	Approver	Qty joined
Assemble	25	☐		10.00000	0.00000	0.00000	LF			☒
Erect	25	☐		10.00000	0.00000	0.00000	LF			☐
Detail	40	☐		10.00000	0.00000	0.00000	LF			☒
Verification & Do	10	☐		10.00000	0.00000	0.00000	LF			☒

5.3.2 Quantity Editing


In InEight Plan you can edit quantities by adding or subtracting quantities from components. The following step-by-step shows how to edit claimed quantity.

Edit Claimed Quantity

- 1. In the **Quantity Tracking** page, select a component.

Quantity claiming changes are best made in the Data Blocks view.

- 2. Find and select the check box to the left of one of the components you created.
- 3. Click the **Edit** icon to open the Edit component slide out panel.



- 4. On the Edit activity component slide out panel, click on the **Claiming History** tab.
- 5. Click on the **Edit** icon for your latest entry.

15%

Edit activity component

CLAIMING CLAIMING HISTORY COMPONENT DETAILS

Install date: 03/17/2020
Increment: 0.37395
Changed date: 03/17/2020
Changed by: Vicky Pierce
Daily plan ID:

Approver: Vicky Pierce

Executor:

Notes:

View full page

Cancel Save and close Save

- You can only change the Approver and Executor, and add notes
- You cannot change the quantity and date information on the left
- This preserves an audit trail to document accurately the claiming of this component

6. Click on the **Claiming** tab.

7. Deselect the **Complete** checkbox for one of your steps.

8. Enter a number in the Installed quantity field of that step.

- Note that the This Period quantity automatically recalculates

Edit activity component

CLAIMING

CLAIMING HISTORY

COMPONENT DETAILS

Step	% Cl...	Com...	Date	Quantity	Install qty	This perio...	UoM	Qty joi...
Shakeout/Trans	15	☐	03/17/2020	2.49300	1.00000	0.00000	Ton	☒
Erect/Bolt Up	45	☐		2.49300	0.00000	0.00000	Ton	☒
Final Torque	30	☐		2.49300	0.00000	0.00000	Ton	☒
Quantity Verific	10	☐		2.49300	0.00000	0.00000	Ton	☒

Approver

Vicky Pierce

Executor

Notes

View full page

Cancel

Save and close

Save

9. When integrated with InEight Design, the Delayed check box lets you mark steps as delayed for further processing on component records.

Edit activity component

CLAIMING

CLAIMING HISTORY

COMPONENT DETAILS

% Cl...	Com...	Date	Quantity	Install qty	This perio...	UoM	Qty joi...	Delayed
100	☐		1.00000	0.00000	0.00000	Each	☒	☐

10. Click **Save**.
11. Click the **Claiming History** tab.

- You can now see your new entry with its negative quantity adjustment along with the original entry.

Batch Edit Claimed Quantity

The following step-by-step shows how to batch edit claimed quantities.

Batch Quantity claiming changes must be made in the Data Blocks view.

1. In the **Quantity Tracking** page, change quantities to one or more components in the Quantity column
2. You can free text and change quantities for multiple components under the quantity column. A blue dot will show unsaved changes.

Actions	Name	Parent record	Assembly	Type	Discipline / Commodity	Claiming scheme	WBS	Quantity	To date quantity	UoV
☒	demo today-copy2			Activity	Electrical	810004 - Install b...	1317	20.00000	0.00000	Ea
☐	demo today-copy			Activity	Electrical	810004 - Install b...	1315	12.00000	0.00000	Ea
☐	demo today-1			Activity	Electrical	810004 - Install b...	1315	2.00000	0.00000	Ea
☐	demo today			Activity	Electrical	810004 - Install b...	1315	8.00000	0.00000	Ea
☐	Everybody	Everybody		Assembly	Anchor Bolts			2.00000		
☐	Everybody	Everybody		Assembly	Anchor Bolts			2.00000		

Displayed results: 30,992 | Selected: 1 | [View selected](#) | [Clear Selection](#)

© 2023 InEight Inc. | [Privacy Statement](#) | [Terms & Conditions](#) | v23.4

3. Click **Save changes**.